v1.14_How to change a password for accessing Admin Panel_Portal Constructor

If packages were installed with default settings, username "admin" and password "password" are used for accessing the Admin Panel and the Portal Constructor.

The password can be changed in the Admin Panel.

To enter the Admin Panel, open your browser and put the server address and the service name into the address bar as follows: http://hostname:8080/wificab/.

To perform authentication, fill in the corresponding fields with the username and the password (admin/password), and then click "*Login*" button or press <Enter>.

Select "Settings", System users" tab. Select the check box next to the item with "admin" login and click "Edit" button.



Change the password in the opened window and click "Confirm".

it : admin	+ ×
Login *	
admin	?
Password *	
	?
Domain *	
root	0
Client`s timezone *	
(+07:00) Asia/Krasnoyarsk	~
Create date	
2018-02-05 17:41:14	
End date	
m	
Family *	
surname	?
Name*	
name	?
Mobile phone *	
79123456789	?
Email	
example@example.ru	?
Description	
	?
🖺 Confirm 🛛 🖉 Canc	el 🛛

The *admin/password* pair is used in configuration files to provide interaction between system modules. Therefore, once the default password was changed, it must be changed in other sections too.

To avoid getting attached to administrator account, change it to "softw/c_service" with "softw/c" default password (it can be changed via the Admin Panel as described in this section). This account will be enough for module interaction. However, it has no access to GUI. The account should be configured/changed in the following sections:

1. GUI EMS. Available on http://hostname:8080/ems/jws . Select "Administration/EMS server configuration/System modules". Choose "softwlc.nbi". Specify "Username" - "softwlc_service", "Password" - "softwlc". Click "Accept".

🐻 System modules settings 🛛 🕹						
mysql	•	Enabled				
passwordGenerator		URL	http://localhost:8080/axis2/services/RadiusNbiService?wsdl			
pcrf		lleornamo	cofful cconico			
portal		Username	Soliwic_Selvice			
softwic.nbi		Password	Jy23mt90			
SSW		Connection timeout, s	30			
system						
tftpserver		Request timeout, s	120			
ti1						
wep						
wop	•					
Actions						
S Reset						
X Reset all						
Accept X Cancel						

2. Portal Constructor. Available on http://hostname:8080/epadmin . Select "System settings/NBI access". Specify "Username" - "softwlc_service", ' Password" - "softwlc". Click "Save".

Portal Constructor	NBI access	English 🗮 👻 🛔
🖨 Dashboard	Protocol	HTTP
🖾 Gallery	Host	localhost
🗱 System settings 🕶	Port	8080
Portal Constructor		
	WSDL path	/axis2/services/RadiusNbiService?wsdl
≓ NBI access	Username	softwlc_service
	Password	
C BRAS access	r	Sava
	L	Save

3. Configuration file "/etc/eltex-apb/apb.properties". Open the file with any available editor, for example "nano /etc/eltex-apb/apb.properties" and specify the parameters:

nbi.client.login=softwlc_service
nbi.client.password=softwlc

To save the changes, press "*Ctrl+o*", and then <Enter> and "*Ctrl+x*" to quit.

4. Configuration file "/etc/eltex-wifi-cab/system.xml". Open the file with any available editor, for example "nano /etc/eltex-wifi-cab/system.xml" and specify the parameters:

<entry key="nbi.serviceLogin.user">softwlc_service</entry>
<entry key="nbi.serviceLogin.password">softwlc</entry>

To save the changes, press "*Ctrl+o*", then <Enter> and "*Ctrl+x*" to quit.

After changing the passwords, restart EMS and tomcat7:

sudo service eltex-ems restart sudo service tomcat7 restart