

v1.14_NBI

- Description
- Starting/stopping procedure
- Configuration
 - [/etc/eltex-radius-nbi/radius_nbi_config.txt](#)
- Configuring hikari cp
- Command documentation

Description

The SOAP-based interface provides connection between SoftWLC components. NBI is used to support the work of the following services: Admin Panel, Portal Constructor, PCRF. It also allows conducting integration with higher OSS/BSS and generating TLS authorization certificates. To install NBI, deploy **eltex-axis** package and then **eltex-radius-nbi** package (follow the order to avoid problems with the service operation).

Starting/stopping procedure

The interface works with tomcat (version 7 and higher), so no specific commands are needed.

Configuration

/etc/eltex-radius-nbi/radius_nbi_config.txt

the file contains parameters for connecting to SoftWLC services.

- Settings for **MySQL** database connection. Different parameters can be used for different databases (connection to **ELTEX_PORTAL** database should definitely be set in the end of the file). As an example, connection to **radius** database is considered:

```
# DB radius(alias=radius)
radius.jdbc.driver=org.gjt.mm.mysql.Driver
radius.jdbc.dbUrl=jdbc:mysql://localhost/radius?
zeroDateTimeBehavior=convertToNull&useUnicode=true&characterEncoding=utf8&relaxAutoCommit=true&connectTimeout=500
radius.jdbc.username=javauuser
radius.jdbc.password=javapassword
radius.jdbc.maxPoolSize=48
radius.jdbc.inUse=yes
```

- **northbound EMS** connection required to send commands to **eltex-ems** service:

```
# ems-northbound
ems.nbi.host=127.0.0.1
ems.nbi.port=8080
ems.nbi.path=northbound
ems.nbi.protocol=http
```

- **SSH** connection to **eltex-auth-service** is needed to restart the service if NAS table is changed via Admin Panel.

```
# eltex_auth_service
auth.port=22
auth.host=127.0.0.1
auth.username=username
auth.password=password
```

- **SSH** connection to **eltex-radius** needed to restart the service if NAS table is changed.

```
# freeradius-domain-1
freeradius-domain-1.port=22
freeradius-domain-1.host=192.168.0.1
freeradius-domain-1.username=username
freeradius-domain-1.password=password
```

- tomcat address available for Admin Panel users. It is used to generate TLS certificates for users and to provide links to log files.

```
# tomcat url
tomcat.host=127.0.0.1
tomcat.port=8080
```

- Address for downloading user TLS certificates. This should be an address of a server available for external network users.

```
# tomcat url
tomcat.host=127.0.0.1
tomcat.port=8080
```

- Connection to **PCRF**:

```
# pcrf stuff
pcrf.enabled=true
pcrf.url=http://localhost:7070
pcrf.username=admin
pcrf.password=password
```

- Connection to **pcrf** database of MongoDB cluster:

```
# pcrf mongodb connector
pcrf.mongodb.enabled=true
pcrf.mongodb.uri=mongodb://localhost:27017/pcrf
```

- Connection to **wifi-customer-cab** database of MongoDB cluster:

```
# wifi-customer-cab mongodb connector
wificab.mongodb.enabled=true
wificab.mongodb.uri=mongodb://localhost:27017/wifi-customer-cab
```

- Settings for SORM2 database connection (Mongo):

```
# Eltex.SORM2.replicator MongoDB 'sorm2' connect
sorm2.mongodb.enabled=false
sorm2.mongodb.uri=mongodb://localhost:27017/sorm2
```

- Connection to SORM2 service:

```
# Eltex.SORM2.replicator host to use API
sorm2.enabled=false
sorm2.url=http://localhost:7071
sorm2.username=admin
sorm2.password=password
```

- SORM3 functionality activation. Verification of Name and Telephone number fields is enabled for an operator when working with Wi-Fi users' accounts. Name and Telephone number fields become compulsory.

```
#It enables records export to SORM3 while editing wifi users  
sorm3.enabled=false
```

- Setting a timeout for statistics loading in Admin Panel. Timeout is set to 90000 ms by default.

```
# wifi-customer-cab request settings  
wificab.timeout=90000
```

Configuring hikari cp

hikari cp connection pool is used for interaction between eltex-radius-nbi and MySQL database.

```
Connection timeout;  
connectionTimeout=15000  
Access validation timeout should be shorter than connectionTimeout;  
validationTimeout=3000  
Idle timeout. It should be in the range from 10000 (10 seconds) to 600000 (600 seconds);  
idleTimeout=30000  
Minimum number of free connections in hikari cp.  
minimumIdle=1
```

Command documentation

Relevant command documentation can be found in eltex-radius-nbi package. It becomes accessible after the package is downloaded via <http://localhost:8080/eltex-radius-nbi/asciidoc/>
WSDL file is available on <http://localhost:8080/axis2/services/RadiusNbiService?wsdl>
(replace localhost with ip address of a server with NBI)