

v1.18_ MongoDB

⋮
⋮
⋮

6-1024 Base64. :

```
openssl rand -base64 741 > mongo_keyfile
```

400, , :

```
chown mongodb mongo_keyfile  
chmod 400 mongo_keyfile
```

/etc/mongod.conf keyfile (keyFile = /etc/mongo_keyfile) MongoDB.

```
service mongod restart
```

keyFile (auth = true).

Mongo shell :

1) admin:

```
$ mongo admin  
connecting to: admin  
>
```

2)

```
db.addUser({ user: "<>", pwd: "<>", roles: [ "clusterAdmin", "userAdminAnyDatabase", "dbAdminAnyDatabase",  
"readWriteAnyDatabase" ] })
```

, Mongo. , **/etc/mongodb.conf** auth = true

```
service mongod restart
```

mongo c .

```
mongo -u<> -p<> admin
```

admin - , , , - .

: notification-gw, pcrf, wifi-customer-cab.

```
, , readWrite (/) dbAdmin( ):
```

```
:
```

```
> use notification-gw
```

```
:
```

```
> db.addUser({ user: "<_>", pwd: "<>", roles: [ "readWrite", "dbAdmin" ] })
```

```
:
```

```
> use pcrf
```

PCRF, , clusterAdmin, replica set:

```
> db.addUser({ user: "<_>", pwd: "<>", roles: [ "readWrite", "dbAdmin", clusterAdmin ] })
```

wifi-customer-cab:

```
> use wifi-customer-cab
> db.addUser({ user: "<_>", pwd: "<>", roles: [ "readWrite", "dbAdmin" ] })
```

/etc/eltex-wifi-cab/system.xml, , wifi-customer-cab.

NBI /etc/eltex-radius-nbi/radius_nbi_config.txt, , pcrf.

NGW /etc/eltex-notification-gw/notification.properties, , notification-gw.